

Garbage Identification (Orin)

Testing based on the trained model can identify the name of the trained object.

1. Main code

Code path:

```
~/dofbot_pro/src/dofbot_basic_visual/scripts/05_Garbage_Identifier.ipynb
```

Import header file

```
#!/usr/bin/env python
# coding: utf-8
import Arm_Lib
import os
import cv2 as cv
import threading
from time import sleep
import ipywidgets as widgets
from IPython.display import display
from dofbot_utils.fps import FPS
from ultralytics import YOLO
from dofbot_utils.robot_controller import Robot_Controller
```

Initialize the posture of the robot arm.

```
robot = Robot_Controller()
robot.move_look_map()
garbage = garbage_identify()
fps = FPS()
model = "General"
```

Initialize model

```
yolo_model = YOLO("./garbage.engine", task='detect')
fps = FPS()
model = "General"
```

Garbage name list:

```
def garbage_getName(self):
    name = "None"
    if self.status == 'waiting':
        self.frame, msg = self.garbage_identify.garbage_run(self.frame)
        for key, pos in msg.items():
            name = key
            if name == "zip_top_can": (self.garbage_num,
self.garbage_class) = ('00', '01')
            if name == "old_school_bag": (self.garbage_num,
self.garbage_class) = ('01', '01')
            if name == "Newspaper": (self.garbage_num,
self.garbage_class) = ('02', '01')
```

```

        if name == "Book":           (self.garbage_num,
self.garbage_class) = ('03', '01')
            if name == "Toilet_paper":      (self.garbage_num,
self.garbage_class) = ('04', '02')
                if name == "Peach_pit":       (self.garbage_num,
self.garbage_class) = ('05', '02')
                    if name == "Cigarette_butts":   (self.garbage_num,
self.garbage_class) = ('06', '02')
                        if name == "Disposable_chopsticks": (self.garbage_num,
self.garbage_class) = ('07', '02')
                            if name == "Egg_shell":        (self.garbage_num,
self.garbage_class) = ('08', '03')
                                if name == "Apple_core":      (self.garbage_num,
self.garbage_class) = ('09', '03')
                                    if name == "Watermelon_rind": (self.garbage_num,
self.garbage_class) = ('10', '03')
                                        if name == "Fish_bone":       (self.garbage_num,
self.garbage_class) = ('11', '03')
                                            if name == "Expired_tablets": (self.garbage_num,
self.garbage_class) = ('12', '04')
                                                if name == "Expired_cosmetics": (self.garbage_num,
self.garbage_class) = ('13', '04')
                                                    if name == "Used_batteries":    (self.garbage_num,
self.garbage_class) = ('14', '04')
                                                        if name == "Syringe":         (self.garbage_num,
self.garbage_class) = ('15', '04')
                                                            if name == "None":          (self.garbage_num,
self.garbage_class) = ('None', 'None')

```

Main thread:

```

def camera():
    # 打开摄像头 Open camera
    capture = cv.VideoCapture(0)
    capture.set(cv.CAP_PROP_FRAME_WIDTH, 640)
    capture.set(cv.CAP_PROP_FRAME_HEIGHT, 480)
    # 当摄像头正常打开的情况下循环执行
    while capture.isOpened():
        try:
            _, img = capture.read()
            fps.update_fps()
            img, msg = garbage.garbage_run(img)
            if len(msg) > 0:
                for name, pos in msg.items():
                    print("name:", name)
        if model == 'Exit':
            cv.destroyAllWindows()
            capture.release()
            break
        fps.show_fps(img)
        imgbox.value = cv.imencode('.jpg', img)[1].tobytes()
    except Exception as e:
        capture.release()
        print(e)
        break

```


First open the system terminal and run roscore

roscore

Program Click the Run Entire Program button on the jupyterlab toolbar, then scroll to the bottom to see the camera component display.



If you put the garbage block face-up in the camera screen at this time, the garbage will be framed and the garbage name will be displayed.



Note: The garbage block must be placed face-up to ensure that the camera screen is facing the garbage icon, otherwise it may not be recognized.

If you need to exit the program, click the [Exit] button.