

Abnormal height sorting of color blocks

Before starting this function, you need to close the process of the big program and APP. If you need to start the big program and APP again later, start the terminal,

```
bash ~/dofbot_pro/APP_DOFBOT_PRO/start_app.sh
```

1. Function description

After the program is started, place color blocks of the same color, and the robot will perform color recognition according to the set HSV value. After pressing the space bar, the robot will lower its claws to grab the color blocks that exceed the height threshold; after placement, it returns to the recognition posture.

2. Start and operate

2.1. Start command

Enter the following command in the terminal to start,

```
#Start the camera:
ros2 launch orbbec_camera dabai_dcw2.launch.py
#Start the underlying control:
ros2 run dofbot_pro_driver arm_driver
#Start the inverse solution program:
ros2 run dofbot_pro_info kinemarics_dofbot
#Start the color recognition program:
ros2 run dofbot_pro_color AnomalyHeightRemoval
#Start the robot gripping program:
ros2 run dofbot_pro_driver grasp
```

2.2. Operation process


After the terminal is started, place blocks of different colors, the camera captures the image, and press the following buttons to process the image:

- [i] or [I]: Enter the color recognition mode, directly load the HSV value calibrated by the last program for recognition;
- 【r】 or 【R】 : reset program parameters, enter color selection mode, select a certain area of the color block with the mouse, obtain the HSV value of this area, release the mouse to enter color recognition mode
- Spacebar: start to grab highly abnormal color blocks


After entering color recognition mode, if the current HSV value still cannot filter out other colors, you can use the dynamic parameter adjuster to fine-tune HSV. Enter the following command in the terminal to start the dynamic parameter adjuster.

```
roslaunch rqt_reconfigure rqt_reconfigure
```

You can modify the HSV value through the slider




As shown in the figure below, when the image on the left (binarization) only shows the only recognized color, click the color image box and press the spacebar. The robotic arm will lower its claws to grab highly abnormal color blocks.



3. Program flow chart

AnomalyHeightRemoval.py



4. Core code analysis

4.1. AnomalyHeightRemoval.py

Code path:

```
/home/jetson/dofbot_pro_ws/src/dofbot_pro_color/dofbot_pro_color/AnomalyHeightRemoval.py
```

Import necessary libraries,

```
import cv2
import rclpy
from rclpy.node import Node
import numpy as np
from message_filters import ApproximateTimeSynchronizer, Subscriber
from sensor_msgs.msg import Image
from std_msgs.msg import Float32, Bool
from cv_bridge import CvBridge
import cv2 as cv

import time
import math
import os
encoding = ['16UC1', '32FC1']
import tf_transformations as tf
import transforms3d as tfs

from dofbot_pro_color.height_measurement import *
from dofbot_pro_interface.msg import *
```

Initialize program parameters, create publishers and subscribers,

```
def __init__(self):
    super().__init__('remove_too_heigher')
    self.declare_param()
    #Robot arm recognizes the posture of the color block
    self.init_joints = [90.0, 120, 0.0, 0.0, 90, 90]
    #Create a publisher for publishing color block information
    self.pub_ColorInfo = self.create_publisher(AprilTagInfo, "PosInfo", 1)
    self.pubPoint = self.create_publisher(ArmJoint, "TargetAngle", 1)
    #Create a subscriber to subscribe to gesture recognition results
    self.grasp_status_sub = self.create_subscription(Bool, 'grasp_done',
self.GraspStatusCallback, 1)
    #Create two subscribers to subscribe to the color image topic and the depth
image topic
    self.depth_image_sub = Subscriber(self, Image, "/camera/color/image_raw",
qos_profile=1)
    self.rgb_image_sub = Subscriber(self, Image, "/camera/depth/image_raw",
qos_profile=1)
    #Time synchronization of color and depth image subscription messages
    self.TimeSynchronizer = ApproximateTimeSynchronizer([self.depth_image_sub,
self.rgb_image_sub], queue_size=10, slop=0.5)
    self.TimeSynchronizer.registerCallback(self.Color_Detect)
```

```

#Save the xy coordinates of the center of the color block
self.y = 0 #320
self.x = 0 #240
#Create a bridge for color and depth image topic message data to image data
self.rgb_bridge = CvBridge()
self.depth_bridge = CvBridge()
#Store the list of x and y values ••of the center value of the identified
color block
self.CX_list = []
self.CY_list = []
#Initialize the region coordinates
self.Roi_init = ()
#Initialize the HSV value
self.hsv_range = ()
#Initialize the information of the recognized color block, which represents
the center x coordinate, center y coordinate and the minimum circumscribed circle
radius r of the color block
self.circle = (0, 0, 0)
#Flag for dynamic parameter adjustment, if True, dynamic parameter adjustment
is performed
self.dyn_update = True
#Flag for mouse selection
self.select_flags = False
self.gTracker_state = False
self.windows_name = 'frame'
#Initialize the state value
self.Track_state = 'init'
#Create a color detection object
self.color = color_detect()
#Initialize the row and column coordinates of the region coordinates
self.cols, self.rows = 0, 0
#Initialize the xy coordinates selected by the mouse
self.Mouse_XY = (0, 0)
#The path of the default HSV threshold file, which stores the last saved HSV
value
self.hsv_text = rospkg.RosPack().get_path("dofbot_pro_color") +
"/scripts/colorHSV.text"
#Load the color HSV configuration file and configure the dynamic parameter
regulator
Server(ColorHSVConfig, self.dynamic_reconfigure_callback)
self.dyn_client = Client(nodeName, timeout=60)
exit_code = os.system('rosservice call /camera/set_color_exposure 50')
#The center xy coordinates of the currently identified color block and the
radius of the minimum circumscribed circle of the color block
self.cx = 0
self.cy = 0
self.circle_r = 0
#The flag for publishing color block information, True means that the color
block information can be published
self.pubPos_flag = False
#Initialize the height value of the color block
self.heigh = 0.0
#Current position and posture of the end of the robot
self.CurEndPos = [-0.006,0.116261662208,0.0911289015753,-1.04719,-0.0,0.0]
#Camera built-in parameters

```

```

self.camera_info_K = [477.57421875, 0.0, 319.3820495605469, 0.0,
477.55718994140625, 238.64108276367188, 0.0, 0.0, 1.0]
#Rotation transformation matrix of the end of the robot and the camera,
describing the relative position and posture between the two
self.EndToCamMat =
np.array([[1.00000000e+00,0.00000000e+00,0.00000000e+00,0.00000000e+00],
[0.00000000e+00,7.96326711e-04,9.99999683e-01,-9.90000000e-02],
[0.00000000e+00,-9.99999683e-01,7.96326711e-04,4.90000000e-02],
[0.00000000e+00,0.00000000e+00,0.00000000e+00,1.00000000e+00]])

```

Mainly look at the image processing function Color_Detect,

```

def Color_Detect(self,color_frame,depth_frame):
    #rgb_image
    #Receive a color image topic message and convert the message data into image
    data
    rgb_image = self.rgb_bridge.imgmsg_to_cv2(color_frame,'bgr8')
    result_image = np.copy(rgb_image)
    #depth_image
    #Receive a depth image topic message and convert the message data into image
    data
    depth_image = self.depth_bridge.imgmsg_to_cv2(depth_frame, encoding[1])
    frame = cv.resize(depth_image, (640, 480))
    depth_image_info = frame.astype(np.float32)
    action = cv.waitKey(10) & 0xFF
    result_image = cv.resize(result_image, (640, 480))
    # Pass the obtained color image as a parameter to process, and also pass the
    keyboard event action
    result_frame, binary = self.process(result_image,action)
    print("self.CX_list: ",self.CX_list)
    print("self.CY_list: ",self.CY_list)
    # Traverse self.CX_list
    for i in range(len(self.CX_list)):
        cx = self.CX_list[i]
        cy = self.CY_list[i]
        #Calculate the depth value corresponding to the center coordinate
        dist = depth_image_info[cy,cx]/1000
        #Put the obtained color block center value coordinates and the depth
        information corresponding to the center point into the compute_heigh function,
        calculate the color block height value and perform a method on it, and change the
        unit from meter to millimeter
        heigh = round(self.compute_heigh(cx,cy,dist),2) *1000
        heigh_msg = str(heigh) + 'mm'
        #Call opencv's putText function to draw the height information on the
        color image
        cv.putText(result_frame, heigh_msg, (cx+5, cy+5), cv.FONT_HERSHEY_SIMPLEX,
0.5, (0, 0, 0), 2)
        #Create a color block information message and assign a value
        pos = AprilTagInfo()
        pos.x = cx
        pos.y = cy
        pos.z = dist
        #Judge whether self.pubPos_flag is 0 and the center corresponding to the
        center of the color block is not 0
        if self.pubPos_flag == True and pos.z!=0:

```

```

        if i==len(self.CX_list) :
            self.pubPos_flag = False
            #If the calculated value is greater than 50, that is, the height is
            higher than 5 cm, then publish the message of the topic of color block
            information
            if heigh>50:
                self.pub_ColorInfo.publish(pos)
                self.pubPos_flag = False
            if len(binary) != 0: cv.imshow(self.windows_name, ManyImgs(1, ([result_frame,
            binary])))
        else:
            cv.imshow(self.windows_name, result_frame)

```

Image processing function self.process,

```

def process(self, rgb_img, action):
    rgb_img = cv.resize(rgb_img, (640, 480))
    binary = []
    #Judge key events. When the space bar is pressed, change the information
    release status. Self.pubPos_flag is True, indicating that the information topic
    can be released.
    if action == 32: self.pubPos_flag = True
    #Judge key events. When i or I is pressed, change the status to
    identification mode.
    elif action == ord('i') or action == ord('I'): self.Track_state = "identify"
    #Judge key events. When r or R is pressed, reset all parameters and enter
    color selection mode.
    elif action == ord('r') or action == ord('R'): self.Reset()
    #Judge the status value. If it is init, it means the initial status value. At
    this time, you can use the mouse to select the area.
    if self.Track_state == 'init':
        cv.namedWindow(self.windows_name, cv.WINDOW_AUTOSIZE)
        #Select the color of an area in the specified window
        cv.setMouseCallback(self.windows_name, self.onMouse, 0)
        #Judge the color selection flag, true means that the color can be
        selected
        if self.select_flags == True:
            cv.line(rgb_img, self.cols, self.rows, (255, 0, 0), 2)
            cv.rectangle(rgb_img, self.cols, self.rows, (0, 255, 0), 2)
            # Check if the selected area exists
            if self.Roi_init[0] != self.Roi_init[2] and self.Roi_init[1] !=
            self.Roi_init[3]:
                #Call the Roi_hsv function in the created color detection object
                self.color, and return the processed color image and HSV value
                rgb_img, self.hsv_range = self.color.Roi_hsv(rgb_img,
                self.Roi_init)
            self.gTracker_state = True
            self.dyn_update = True
        else: self.Track_state = 'init'
    #Judge the status value. If it is "identify", it means that color recognition
    can be performed.
    elif self.Track_state == "identify":
        # Check if there is an HSV threshold file. If so, read the value in it
        and assign it to hsv_range

```

```

        if os.path.exists(self.hsv_text): self.hsv_range =
read_HSV(self.hsv_text)
        #If it does not exist, change the state to init to select the color
        else: self.Track_state = 'init'
        if self.Track_state != 'init':
            #Judge the length of the self.hsv_range value, that is, whether the value
exists. When the length is not 0, enter the color detection function
            if len(self.hsv_range) != 0:
                rgb_img, binary, self.CX_list, self.CY_list =
self.color.ShapeRecognition(rgb_img, self.hsv_range)
                #The flag for determining dynamic parameter updates. True means that
the hsv_text file can be updated and the value on the parameter server can be
modified.
                if self.dyn_update == True:
                    write_HSV(self.hsv_text, self.hsv_range)
                    params = {'Hmin': self.hsv_range[0][0], 'Hmax': self.hsv_range[1]
[0],
                                'Smin': self.hsv_range[0][1], 'Smax': self.hsv_range[1]
[1],
                                'Vmin': self.hsv_range[0][2], 'Vmax': self.hsv_range[1]
[2]}

                    self.dyn_client.update_configuration(params)
                    self.dyn_update = False
        return rgb_img, binary

```

4.2、grasp.py

Please refer to the content of [grasp.py] in section 4.2 of the tutorial [Three-dimensional space sorting and gripping\1. Machine code ID sorting].