

Object Recognition (Jetson-Nano)

By using OpenCV to call YOLOv4-tiny for object recognition and detection, the names of most objects can be identified.

Note:

1. Before starting the program, please follow the [Assembly and Installation Tutorial] -> [Install Map] tutorial to correctly install the map before proceeding.
2. This example runs on the host machine; simply open a web browser and enter the IP address:8888

1. Code path

1. Code path

```
~/dofbot_ws/src/dofbot_basic_visual/scripts/06.Object_Recognition/06.Object_Recognition.ipynb
```

2. File Configuration

First, we need to import the yolov4-tiny network model structure cfg file, the network weights file, and the COCO dataset classification names txt file. (Here, we directly use the official YOLOv4 dataset and model.)

3. Object Detection

3.1 Building the Model Network Structure

First, we use the **cv2.dnn.readNet()** function to construct the CSPDarknet53 network structure, passing in the model structure cfg file and the network weights file. OpenCV provides several methods for image classification, detection, and segmentation for its neural network modules, automatically performing preprocessing and post-processing of input images. Here, we use the object detection module **cv2.dnn_DetectionModel()**, passing in the network model.

```
self.net = cv2.dnn.readNet('yolov4-tiny.cfg', 'yolov4-tiny.weights')
self.model = cv2.dnn_DetectionModel(self.net)
```

3.2 Target Detection Methods

```
classids, scores, bboxes = self.model.detect(image, confThreshold,
numsThreshold)
```

Parameters:

frame: The input image

confThreshold: The confidence threshold used to filter the bounding boxes; the minimum confidence score for object detection.

numsThreshold: A custom threshold for non-maximum suppression.

Return Value:

classIds: Class index

confidences: Confidence score; the probability that a bounding box belongs to a certain class.

boxes: Bounding box information: top-left corner coordinates (x, y), width and height of the box (w, h).

3.3 Setting Model Input Parameters

```
self.model.setInputParams(size=(320,320), scale=1/255)
```

size indicates how large the input image will be scaled. A larger size results in better detection performance, but slower detection speed. **scale** indicates the scaling factor for pixel values.

4. Main Code

Importing various libraries and model files

```
#!/usr/bin/env python
# coding: utf-8
import Arm_Lib
import cv2 as cv
import threading
from time import sleep
import ipywidgets as widgets
from IPython.display import display
from Object_recognition import Object_recognition_identify
```

Object recognition function

```
def detect_image(self, image):

    classids, scores, bboxes = self.model.detect(image, 0.5, 0.3)

    for class_id, self.score, bbox in zip(classids, scores, bboxes):
        self.x, self.y, self.w, self.h = bbox
        self.class_name = self.classes[class_id]

        cv2.rectangle(image, (self.x,self.y), (self.x+self.w,self.y+self.h),
(255,255,0), 2)

        cv2.putText(image, self.class_name, (self.x,self.y+self.h+20),
cv2.FONT_HERSHEY_COMPLEX, 1, (0,255,0), 2)

        cv2.putText(image, str(int(self.score*100))+'%', (self.x,self.y-5),
cv2.FONT_HERSHEY_COMPLEX, 1, (0,255,255), 2)

    return image
```

List of object names:

```
1 person
2 bicycle
3 car
4 motorbike
5 aeroplane
6 bus
7 train
8 truck
9 boat
10 traffic light
11 fire hydrant
12 stop sign
13 parking meter
14 bench
15 bird
16 cat
17 dog
18 horse
19 sheep
20 cow
21 elephant
22 bear
23 zebra
24 giraffe
25 backpack
26 umbrella
27 handbag
28 tie
29 suitcase
30 frisbee
31 skis
32 snowboard
33 sports ball
34 kite
35 baseball bat
36 baseball glove
37 skateboard
38 surfboard
39 tennis racket
40 bottle
41 wine glass
42 cup
43 fork
```

main thread

```
def camera():
    # 打开摄像头 Open camera
    capture = cv.VideoCapture(0)


    while capture.isOpened():
        try:
            _, img = capture.read()
            img = cv.resize(img, (640, 480))
            img = ob_re.detect_image(img)
            if model == 'Exit':
```

```
cv.destroyAllWindows()
capture.release()
break
imgbox.value = cv.imencode('.jpg', img)[1].tobytes()
except KeyboardInterrupt:capture.release()
```

Click the "Run the whole program" button on the JupyterLab toolbar, then scroll to the bottom to see the camera component displayed.



At this point, placing a recognizable object into the camera's view will allow it to be framed and its name displayed.



Exit

If you need to exit the program, please click the "Exit" button.

